
Number of rows

Posted by fritschle - 2011/05/12 01:27

I might be missing a post about this but I looked through them and couldn't find any info.

I'm trying to change the number of rows displayed. Using Joomla 1.6. Just purchased Data Tables on 5/9/11. Newest version.

I changed the number of rows to 15 but it didn't show the extra 5. Still only showing 10. The pagination works and I can change the amount of rows to 25 with the drop down selector.

Not sure if this is a bug or if I have something set wrong. My settings are below.

Any help would be appreciated.

Thanks. Kyle

Include MooTools - no
Include jQuery - yes
jQuery noConflict - yes
jQuery UI Theme - smoothness
Show loading pane - no
Loading message - loading...
Module Class Suffix - blank

HTML table settings

Caption - blank
Advanced styling - yes
Show header - yes
Show footer - no
Width - 100%
Cell padding - 0
Cell spacing - 0
Border - 0
Border collapse - seperate
Table CSS class - blank
Rows CSS classes - blank

Columns settings - all blank, didn't edit

CSS Styles - .dataTables_wrapper {color: #000; }

Choose table type
ARI Data Table

Choose custom paging mode
Simple

Custom pagination - blank
Using jQuery UI themes - no
Scroll Height - 280
Scroll Width - blank
Using paging - yes
Pagination type - next / prev
Paging list - yes
Save state - no
Duration of cookie - 7200
Filter - yes
Sorting - yes

Columns settings - didn't edit

Table information - yes
Show processing - yes
Auto width - yes
Number of rows to display - 15

every thing below this is standard, didn't change any options except where to find the cvs file.

=====

Re: Number of rows

Posted by admin - 2011/05/12 05:08

Hello,

Could you provide link to page where we can see the problem?

Regards,
ARI Soft

=====

Re: Number of rows

Posted by fritschle - 2011/05/20 02:32

The site is www.bluegrasscasing.com

I'm not sure what you're going to be able to tell from the front end. It works fine displaying 10 rows to begin with but can't change to auto display 15 instead.

Thanks for your help.

=====

Re: Number of rows

Posted by admin - 2011/05/20 05:20

Hello,

Default page size can be defined with help "ARI Data Tables -> Page size" parameter. Values of this parameter should be one of value from "ARI Data Tables -> Page size option" parameter. In your case set "Page size" parameter to "25".

Regards,
ARI Soft

=====