Column settings Posted by cnewell - 2011/11/18 18:21
I am having problems manipulating column width and allowing links
I am using an ARI Data Table and its source is a csv file.
Directions read,
"Columns settings:
Use 'Columns settings' parameter for this purpose. At first specify column ID or index (column index is zero-based) in 'ID' column that indicate what column you want to configure. After this the following parameters can be defined: "
When I enter information into the column setting it doesn't change anything in the table.
Re:Column settings Posted by admin - 2011/11/18 18:52
Hello,
Could you provide a screenshot with configuration "Columns settings" parameters section and a link to a page where we can see table?
Regards, ARI Soft
Re:Column settings Posted by cnewell - 2011/11/18 19:50
http://www.ari-soft.com/images/fbfiles/images/column_settings.jpg
Re:Column settings Posted by cnewell - 2011/11/18 19:51
http://www.ari-soft.com/images/fbfiles/images/column_settings2.jpg
Re:Column settings Posted by cnewell - 2011/11/18 19:52
Re:Column settings Posted by cnewell - 2011/11/18 19:56

Re:Column settings Posted by cnewell - 2011/11/18 19:59
Can't give you a live link, because the site is under construction and closed.
As you can see the setting I enter for column width and Regognize links don't take effect in the website after I save it loomla and review it on the frontend
Re:Column settings Posted by admin - 2011/11/18 20:52
We suppose "Choose table type -> ARI Data Table -> Auto width" parameter is set to "Yes".
Regards, ARI Soft
Re:Column settings Posted by cnewell - 2011/11/18 20:59
No actually I've tried setting that parameter to know it changes nothing in the column width or the recognize link
Re:Column settings Posted by admin - 2011/11/18 21:02
Provide a link to a page where we can see the table.
Regards, ARI Soft
Re:Column settings Posted by cnewell - 2011/11/18 21:10
nttp://trustedfarms.com/resources/where-to-buy
Re:Column settings Posted by corkcork - 2011/12/03 23:28
am having the same problem. i don't know how to change the column widths. Where do I find the ID of the column? he width measured in pixels? How do I do this?
Re:Column settings Posted by admin - 2011/12/04 08:11

Regards, ARI Soft

Re:Column settings Posted by admin - 2011/12/05 06:49

Try to add use the next code in "CSS Styles" parameter in module settings:

```
{$id} .ari-tbl-col-INDEX
width: 100px;
```

Where INDEX is zero-based column index, for example if you want to set width to 100px for the first column and 75px for the second column, add the next code:

```
{$id} .ari-tbl-col-0
width: 100px;
{$id} .ari-tbl-col-1
width: 75px;
```

Regards, **ARI Soft**